

How to set barcode margins with barcode sdk in C# and ByteScout Premium Suite

Step-by-step tutorial on how to set barcode margins with barcode sdk in C#

The sample source codes on this page shows how to set barcode margins with barcode sdk in C#. ByteScout Premium Suite can set barcode margins with barcode sdk. It can be applied from C#. ByteScout Premium Suite is the bundle that includes twelve SDK products from ByteScout including tools and components for PDF, barcodes, spreadsheets, screen video recording.

The SDK samples given below describe how to quickly make your application do set barcode margins with barcode sdk in C# with the help of ByteScout Premium Suite. Simply copy and paste in your C# project or application you and then run your app! Complete and detailed tutorials and documentation are available along with installed ByteScout Premium Suite if you'd like to learn more about the topic and the details of the API.

ByteScout provides the free trial version of ByteScout Premium Suite along with the documentation and source code samples.

FOR MORE INFORMATION AND FREE TRIAL:

[Download Free Trial SDK \(on-premise version\)](#)

[Read more about ByteScout Premium Suite](#)

[Explore API Documentation](#)

[Get Free Training for ByteScout Premium Suite](#)

[Get Free API key for Web API](#)

[visit www.Bytescout.com](http://www.Bytescout.com)

Source Code Files:

```
using System;
using System.Collections.Generic;
using System.Text;
using System.Diagnostics;

using Bytescout.BarCode;

namespace Sample
{
    class Program
    {
        static void Main(string[] args)
        {
            // Create new barcode
            Barcode barcode = new Barcode();

            // Set symbology
            barcode.Symbology = SymbologyType.Codabar;
            // Set value
            barcode.Value = "123456";

            // Set new margins
            barcode.Margins = new Margins(0, 0, 100, 100);

            // Save barcode to image
            barcode.SaveImage("result.png");

            // Show image in default image viewer
            Process.Start("result.png");
        }
    }
}
```

VIDEO

<https://www.youtube.com/watch?v=NEwNs2b9YN8>

[60 Day Free Trial](#) or [Visit ByteScout Premium Suite Home Page](#)
[Explore ByteScout Premium Suite Documentation](#)
[Explore Samples](#)
[Sign Up for ByteScout Premium Suite Online Training](#)

ON-DEMAND REST WEB API

[Get Your API Key](#)
[Explore Web API Docs](#)
[Explore Web API Samples](#)

[visit www.Bytescout.com](http://www.Bytescout.com)

[visit www.PDF.co](http://www.PDF.co)

www.bytescout.com